

## Getting Started with OverDrive eBooks on Adobe Digital Editions

When direct download is not available, use Adobe Digital Editions (ADE) to add an OverDrive eBook to a Kobo eReader.

Adobe Digital Editions is now managed by [ByteBooks](#). As of June 23, 2026, a ByteBooks ID will be required to authorize ADE software instead of an Adobe ID.

### Install Adobe Digital Editions (ADE)

Go to <https://www.adobe.com/ca/solutions/ebook/digital-editions/download.html> to download and install Adobe Digital Editions (ADE) software on your desktop computer.

### Create an ByteBooks account (ByteBook ID)

1. Go to <https://dtsbytebooks.com/transition-help>. If you already have an Adobe ID and you would like your account information transferred, select **Already have an Adobe ID account**. Otherwise, select **Create Your ByteBooks Account**.
2. Create your ByteBooks account by entering your name, email address, country and a password of your choice. Select **Create Account & Verify**.
3. ByteBooks will send a verification email to your email address. Open the email message to find the six digit One Time Password (OTP). Enter the OTP code where indicated on the ByteBooks website to finalize the set up of your ByteBooks ID.

### Authorize Adobe Digital Editions (ADE) with an ByteBooks ID

1. Open ADE and select on **Help**. Click on **Authorize Computer**.
2. Confirm the **eBook Vendor** box has **Adobe ID** selected. ByteBooks is not an option at this time.
3. Enter the email address and the password used to create your ByteBooks account. Select **Authorize**.
4. With Adobe Digital Editions open, connect your Kobo eReader to your computer using the USB cable supplied. Select **Connect** on the Kobo eReader's screen. Leave the eReader plugged into the computer.
5. In ADE, **Kobo eReader** will appear under Devices on the left-hand side of the screen. This may take a few minutes.
6. Click on **Kobo eReader** to select it. Select the **Device Options** button (settings wheel) and select **Authorize Device**. If your device was previously authorized with your Adobe ID, Authorize Device may not be an available option. Select **Erase Device Authorization** first then **Authorize Device**.

### Find and download ebooks

1. Go to the Toronto Public Library's OverDrive website at [tpl.ca/overdrive](http://tpl.ca/overdrive).

2. Select **Search** to find a book by title, author or series. Select **Collections** to browse. Look for the eBook indicator to select the eBook format of a title.
3. Select **Borrow** to check out the book and enter your library card number and PIN (usually the last four digits of your phone number) to sign in.
4. Go to your Loans page under My Account and select the **Download** button next to the book cover.
5. The browser may automatically open the acsm file for this ebook. If not, click on Open (if available) or double-click on the downloaded acsm file (check Downloads folder on computer) to start the authorization process that will download the ePUB file and open the ebook in Adobe Digital Editions.

### Transferring ebooks to a Kobo eReader

1. The downloaded title will open in Reading view in ADE. Click on **Library** in the upper left-hand corner to switch to Library view.
2. Click on the book cover and drag and drop the title to your Kobo eReader (listed under Devices) or right-click on the cover and select **Copy to Computer/Device** and then **Kobo eReader**.
3. Click on Kobo eReader under Devices in ADE and confirm that the ebook is available on your eReader. Safely eject your eReader from your computer.
4. After a moment, the ebook will be available in the My Books section of your eReader.

### Returning ebooks

OverDrive eBooks will automatically expire at the end of the lending period. They can also be returned early. Help to keep waiting times short by returning borrowed items once you are finished.

Open ADE on your computer and connect the Kobo eReader to the computer with a USB cable.

1. Select **Connect** on the screen of the Kobo eReader. Leave the eReader connected to the computer.
2. In ADE, click on **All Items** under Bookshelves on the left. Right click on the cover of the ebook to be returned. Left click on **Return Borrowed Item**.
3. Under Devices, click on **Kobo eReader**.
4. Right click on the cover the ebook that you just returned. Left click on **Remove from Library**.

### More Help:

For more information, contact ByteBooks support at [ebooks-support@wipro.com](mailto:ebooks-support@wipro.com) or Kobo Help at <https://help.kobo.com/hc/en-us/articles/360019374554-Borrow-eBooks-from-the-public-library-using-your-library-s-website>.